



Infinity Connect Desktop Client

User Guide

Software Version 1.8

Document Version 1.8.a

June 2021

]pexip[

Contents

Introduction	3
Installing the Infinity Connect desktop client	3
Getting started	4
Registering your client to receive calls and use the directory	5
Configuring your client	5
Making a call	7
Receiving a call	11
Using in-call controls	11

Introduction

All you need to do to make a call into a Pexip Infinity environment using the Infinity Connect desktop client is [install it](#), [enter your name](#), and then [enter the alias](#) of the person or conference you want to call. This guide tells you how to do this, as well as providing information on using all the other available features.

Installing the Infinity Connect desktop client

i No special privileges are required to install the Infinity Connect desktop client, as it is installed in a per-user context.

To install the Infinity Connect desktop client, go to the [Pexip App download page](#) and download and install the appropriate file for your operating system as described below.

Note that 32-bit operating systems are not supported with the Infinity Connect desktop client.

Windows

(Supported on Windows 10.)

Download the `pexip-infinity-connect_<release>_win-x64.msi` file for Windows.

Double-click on the `.msi` file to install the Infinity Connect desktop client and then follow the instructions in the installation wizard. During the installation process the Infinity Connect icon is added to the desktop, and entries are added to the Windows registry to allow links prefixed with `pexip:` and `pexip-provision:` to open automatically in the Infinity Connect desktop client.

macOS

(Supported on macOS 10.11 and later.)

Download the `pexip-infinity-connect_<release>_darwin-x64.dmg` file for macOS.

To install the macOS client, open this file and drag the **Pexip Infinity Connect.app** into the **Applications** folder.

Linux

Download the `pexip-infinity-connect_<release>_linux-x64.tgz` file for Linux.

To install the Linux client:

1. Create a new directory. For example, to install the client for a single user "alice":

```
mkdir /home/alice/pexapp  
cd /home/alice/pexapp
```
2. Download the Infinity Connect desktop client `tgz` file to that directory and extract the archive. For example:

```
tar -xzf pexip-infinity-connect_<release>_linux-x64.tgz
```
3. Copy the `.desktop` file to the appropriate location for making the application available for this user as per freedesktop.org-compliant desktop guidelines (see <https://developer.gnome.org/integration-guide/stable/desktop-files.html.en> for more information). For example:

```
cp pexip-infinity-connect_linux-x64/pexip-infinity-connect.desktop /home/alice/.local/share/applications/pexip-infinity-connect.desktop
```
4. Using your preferred text editor, modify the `Exec` line to point to the location of the `pexip-infinity-connect` binary on your system. For example:

```
emacs /home/alice/.local/share/applications/pexip-infinity-connect.desktop
```

and make it look something like this:

```
[Desktop Entry]  
Name=Pexip Infinity Connect  
Exec=/home/alice/pexapp/pexip-infinity-connect_linux-x64/pexip-infinity-connect  
Terminal=false  
Type=Application  
Icon=application-x-executable
```


Note that if you want to install the application for all users (rather than just a single user), follow the same instructions but instead copy the `.desktop` file into the `/usr/share/applications` directory (you may need root privileges to do this).

Getting started


Your administrator may have provided you with a link that will automatically configure your Infinity Connect client with your personalized details (such as your name and registration settings). Otherwise, the first time you use your Infinity Connect desktop client, you'll be asked to provide your name. The desktop client uses your default camera, microphone and speakers, but you can change these if required.

That's all you need to do before you [make a call](#), but there are also some [additional settings](#) you can configure.

1. If prompted, enter your name:




2. If required, turn on your camera and microphone by clicking on the icons in the middle and bottom right of the video window:



- i** If you are joining a meeting where you might not be speaking often, or where there will be many other participants, it is good practice to turn off your microphone before placing the call, and turn it on only when you are in the meeting and wish to speak.

3. If required, select the **Settings** icon ●●● underneath the video window to select which camera, microphone and speakers to use:




Registering your client to receive calls and use the directory

When your Infinity Connect client is registered, as well as being able to receive calls, you can filter and lookup the contact details (phone book / directory) of other devices or VMRs that are set up on the Pexip Infinity platform.

Your administrator may have provided you with a link that will automatically configure your Infinity Connect client with your personalized registration details.






If you need to manually configure your Infinity Connect client:








1. Go to the **Settings** screen (from the Infinity Connect home screen, under the main video window, select **Settings** ●●●).
2. Select  **Registration**.
3. Enter the **Registration Host**, **Alias**, **Username** and **Password** provided to you by your administrator. Be aware that these fields are case-sensitive, and some devices default to uppercase for the first character of the user name.
4. Select **Register**.

When you have successfully registered, the button changes to **Unregister** and the icon at the top right of the **Registration** page appears green.

You don't need to register your client to make calls, only to receive them.

Configuring your client

Setting	Description
Home page	
Name	<p>The name that appears to other conference participants.</p> <p>You're asked to enter your name the first time you use the client, but you can change your name from the home page by clicking on it.</p> <p>For desktop client users, your name may already have been pre-filled if your administrator has sent you a link that automatically applies your personalized settings to your client, but it can still be overwritten.</p>
●●● Settings	
 (Camera)	<p>Shows the currently selected camera. Select this option to change the camera to use.</p> <p>When the selected camera is working properly, your self view is shown in the main video window.</p> <p> If you select <i>None</i>, you will join the meeting without a camera, but you can still see everyone else's video.</p>
 (Microphone)	<p>Shows the currently selected microphone. Select this option to change the microphone to use.</p> <p>When the selected microphone is working properly, a green bar appears under the main video window when audio is detected. The length of the bar represents the level of audio volume being picked up by the microphone.</p> <p> If you select <i>None</i>, you will join the meeting without a microphone, but you can still hear everyone else's audio.</p>
 (Speakers)	<p>Shows the currently selected speakers or headset. Select this option to change the speakers to use.</p> <p>To check that the selected speakers are working properly, select the speaker icon from the bottom left of the main video window and then select the speaker to use. A tone will be played from that speaker.</p>

Setting	Description
 Bandwidth *	<p>The maximum bandwidth for the call, and the bandwidth at which the initial call attempt is made. Note that calls may be temporarily downspeeded due to network conditions.</p> <p>The default is <i>Medium (up to 1264kbps)</i>, but if you are on a cellular connection or slow Wi-Fi connection you may want to reduce this to <i>Very Low (up to 256kbps)</i>.</p> <p>You should also reconnect using a lower bandwidth if you experience slow or low-quality video.</p>
 Languages *	<p>(Only applies if additional languages have been enabled by your administrator.)</p> <p>Allows you to select from a drop-down menu the language to use in your Infinity Connect client.</p> <p> If your browser or device's default language is supported by the Infinity Connect client, that language is used automatically. Alternatively, your administrator may have specified a default language to use.</p>
 Registration	
Registration Host *	The domain, FQDN or IP address of the server to which registration requests are sent. This should be the IP address or FQDN of a local Conferencing Node.
Alias	The alias that this client will register with. This is the alias that other users should dial when they want to call this client.
Username / Password	<p>The username and password to use when this device registers to Pexip Infinity and is not using Single Sign-On (SSO) services, such as AD FS.</p> <p>If the client is configured for SSO, you will be asked to sign in to an alternative authentication service.</p>
<p> The registration fields are read-only when the client is successfully registered — you must Unregister if you want to change them. When a client has been configured (provisioned) with SSO registration information, the Username / Password fields are blank and the registration settings can only be modified by resetting the app.</p>	
 Advanced settings	
Confirm when disconnecting *	When this option is selected, you must confirm each time you wish to disconnect from a meeting. This prevents you from accidentally disconnecting yourself. This is on by default.
View incoming presentation in full motion *	<p>This setting determines how presentations from other participants are initially received by you.</p> <p>Presentations can be received in two formats:</p> <ul style="list-style-type: none"> A lower-bandwidth series of still images (suitable for documents and screens being shared). With this option, Pexip Infinity periodically takes a snapshot of the presentation and converts it to JPG format, and sends that to the Infinity Connect client at between 0.5 to 1 fps. For this reason, presentations that contain a lot of movement may appear jerky to clients using this option. A higher-bandwidth full motion stream (suitable for presentations with a lot of movement). With this option, Pexip Infinity sends the presentation to the Infinity Connect client as a video stream at up to 30 fps, so movement will appear smooth. <p> The actual frame rate used depends on the capabilities of the endpoint that is sending the presentation. Infinity Connect clients can send presentations at up to 30 fps; other clients may send at a higher or lower frame rate.</p> <p>This setting is off by default: presentations are initially received as still images, and you can subsequently elect to view them in full motion by selecting the HD button at any time during the call. However, when View incoming presentation in full motion is selected, presentations received by you are always shown in full motion by default, and you can then elect to view them as still images.</p>
Send anonymous statistics *	When this option is selected, anonymous information about how the client is being used is sent to Pexip. This is on by default.

Setting	Description
Play ringtone on incoming calls *	This is on by default; if you do not want to hear the default ringtone when you are receiving an incoming call, you can de-select this option.
Start application in background *	The client will always start automatically when the device it is installed on starts. This option allows you to select whether it starts minimized (in the background), or maximized (in the foreground). If you have previously entered your registration details the client will also register on startup. If you are configured for SSO, you may be asked to sign in to your alternative authentication service, such as AD FS. This is off by default.
High contrast *	When this option is enabled, there is a higher contrast between foreground and background elements of the user interface, making them more legible. This is off by default.
Device pairing	This setting toggles the availability of the option to pair with an alternative device when placing a call. This is on by default.
Screen sharing quality	This setting determines the maximum frame rate used when you share your screen with other participants. A lower frame rate results in images with more <i>Sharpness</i> and is best for static presentations; a higher frame rate is less sharp and is best for content where there is more <i>Motion</i> . The default is 2 frames per second; the maximum is 15fps for the desktop client. Note that the actual frame rate at which a presentation is sent will depend on the browser, computer, network quality, and nature of the presentation.
Import trusted key	If customized branding or configuration has been applied to the client, you have to load a trusted key and confirm that you want to apply the customizations before they can take effect. Your administrator needs to supply you with the appropriate key file.






About this app

Reset app	The Reset option clears the app storage and any registration settings.
Logs	If you are having issues with your Infinity Connect client, your administrator may ask you to Open log folder to obtain logging information about the last call.



* The administrator can provide a first-time default for this option.

Making a call

What	How
Joining a call with audio and video	<ol style="list-style-type: none"> Ensure that your camera and microphone are enabled and working correctly: <ul style="list-style-type: none"> You should see your own image in the video window. The microphone icon should be green  and you should see a green bar under the video image indicating the volume of audio being detected. Select  . In the box at the top right of the window, enter the address of the person or meeting you wish to join: <div data-bbox="402 1696 1149 1789" style="border: 1px solid #ccc; border-radius: 10px; padding: 10px; display: inline-block; margin: 5px;"> <p>meet.alice@example.com</p> </div>  Either click on the icon to the right of the box, or press enter.

What	How
------	-----

Joining a call with audio only

1. Ensure that your microphone icon is green  and you see a green bar under the video image indicating the volume of audio being detected.
2. Select  .
3. In the box at the top right of the window, enter the address of the person or meeting you wish to join:




4. Either click on the icon to the right of the box, or press enter.

When you join the call, you'll be able to hear other participants and they'll be able to hear you, and you can send and receive content, but you can't send or receive any video. Instead, in the main video window there is an infographic of the participants in the call:



Joining a meeting as a presentation and control-only participant

1. Select  .
2. In the box at the top right of the window, enter the address of the meeting you wish to join:



3. Either click on the icon to the right of the box, or press enter.

You'll join the meeting as a presentation and control-only participant - you won't send any audio or video, and you won't receive any audio or video from other participants. However, you'll be able to view content that others are sharing, and share content with others. You'll also have access to the participant list and events, and be able to control the conference (if you are a Host).

Entering the PIN

For some meetings, you are offered the ability to enter a PIN. If this is your VMR, enter your Host PIN. If not, the meeting organizer should have told you the PIN to use. If you haven't been given a PIN, select Join to join as a Guest:







×

Welcome to the meeting



or just

The PIN determines whether you join the meeting as a Host or Guest. Hosts can control the meeting and the other participants; Guests can't control the meeting but can still see and hear the other participants, and share content.

Other ways to select the person or meeting to call


What	How
Directory	<p>When your Infinity Connect client is registered, as well as being able to receive calls, you can filter and lookup the contact details (phone book / directory) of other devices or VMRs that are set up on the Pexip Infinity platform. You do this by typing part of the address of the person or the name of the VMR you want to call; everything that contains the letters you've typed will appear in the Directory section beneath.</p> 
Favorites	<p>You can add the addresses of people or meetings you call frequently to your Favorites list.</p> <p>To do this:</p> <ol style="list-style-type: none">1. Select the add icon  to the right of the Favorites section.2. Enter the address of the person or meeting room, and the name you want to remember it by:  <ol style="list-style-type: none">3. Select the  icon or press enter. <p>You can also add a favorite from the Recents list (see below).</p>
Recents	<p>The addresses of any people or meetings you have previously called, or received calls from, are shown in the Recents list.</p> <ul style="list-style-type: none">• To call anyone in this list again, simply click on the address. You can't return a call received directly from another person. In this case, you'll see "No dial back" after their name.• To use an address in the list as a basis for a new address to call (for example if you have mis-typed an address), select the edit icon  to the right of the address. The existing address appears in the box at the top of the list; from here you can edit it before placing the call.• To add an address in the list to your Favorites (see above), select the star icon  to the right of the address.

Advanced options

What	How
Pairing with an alternative video/audio device	<p>You can use your Infinity Connect client to pair with another video (or audio) device. When paired, your Infinity Connect client will join the meeting as a presentation and control-only participant, and the paired device will join with video (or audio). Paired devices are added automatically to any Virtual Meeting Room or Virtual Auditorium you join as a Host from your Infinity Connect client. The paired device is disconnected automatically from the meeting when you disconnect your client.</p> <p>Pairing is useful if, for example, you often make calls from a dedicated meeting room with a videoconferencing endpoint that you use for the main video, but you also want to use your Infinity Connect client to control the meeting and view content.</p> <p>To pair with an alternative device:</p> <ol style="list-style-type: none"> From the bottom of the call panel, select Pair with a device. From the Device Pairing panel, select the + icon in the top right corner. Enter the address of the device, and the name that you want to remember it by. <ul style="list-style-type: none"> i By default, the paired device is set to Showing presentation on this device, meaning that any content being shared, as well as the main video, is shown. If you don't want content to be sent to the device (for example, if you intend to view content on your Infinity Connect client), click on the option; it changes to Presentation hidden on this device, meaning that the device will only show the main video stream. Click the option again to toggle back to showing content. Select the ✓ icon or press Enter. The new device appears in the list. To use it for your next call, click on it - the selected device appears in blue:  <ol style="list-style-type: none"> To return to the main call page, select the < icon at the bottom left of the panel. <p>Now, at the bottom left of the home screen you'll see Calling using followed by the name of the selected paired device:</p>  <p>When a paired device is selected, whenever you place a video (or audio-only) call to a VMR, the selected device is added to that VMR as a video (or audio-only) participant, and your connect client joins the VMR as a presentation and control-only participant.</p> <p>To stop using the additional device:</p> <ol style="list-style-type: none"> Click on the Calling using ... link at the bottom left of the home screen. From the list of devices, select Default. <p>The button at the bottom of the call panel changes to Pair with a device — this means that only your connect client will be used the next time you place a call.</p>


Receiving a call

When someone calls your endpoint by dialing the **Alias** you have registered with, you get an incoming call alert at the bottom right of your screen showing the name and address of the person or meeting room who is calling you:






When you click on this alert or open your Infinity Connect client you get the option to answer with video or audio only. You can also select the **Settings** (three dots) icon to select the camera, microphone and speakers to you wish to use before you answer the call.






Alternatively, to decline the call, select the **Dismiss** button at the top right of the alert:

















You also hear an audio alert; you can disable this by going to **Settings > Advanced Settings** and deselecting **Play ringtone on incoming calls**.






Using in-call controls














What	How	Keyboard shortcut
Enter Host PIN (if joined as Guest) 	From the toolbar at the bottom of the screen, select Enter Host PIN .	
Change your camera, microphone or speakers during a call 	<ol style="list-style-type: none"> From the top of the side panel, select Control (three dots). Select Select media devices. Select the camera, microphone or speakers/headset, and then choose a new one from the list of available options. 	
Pin a minimized version of the client to your screen 	From the toolbar at the bottom of the screen, select Open minimized view . The Infinity Connect application window will shrink and be pinned on top of all your other application windows, and you can drag it to a suitable location. To return the window to its previous size, select Open maximized view .	






What	How	Keyboard shortcut
<p>Share your screen with all other participants</p> 	<ol style="list-style-type: none"> From the toolbar at the bottom of the window, select Share my screen. Select the window or screen you want to share. <p>When you are sharing, the icon changes to blue. To stop sharing, select the Stop presenting button.</p> <p>i The best way to share a PowerPoint presentation is to start the Slide Show from within PowerPoint first, and then tab to Infinity Connect, share your screen, and select the Slide Show window.</p> <p>Note that the ability to present into a conference may have been restricted to Hosts only.</p>	
<p>Share images or PDFs with all other participants</p> 	<ol style="list-style-type: none"> From the toolbar at the bottom of the screen, select Present files. <p>The Presentation screen appears:</p>  <ol style="list-style-type: none"> Select +, or drag and drop the file(s) you want to share into the Presentation window. You can add multiple files, and they can be a combination of images (JPEG, BMP, PNG or GIF) and PDFs (if supported by your device). Each image and PDF page is converted into an individual slide. By default, every slide is selected for presenting, but you can click on individual slides to select and deselect them:  <ol style="list-style-type: none"> When you have selected all the slides you want to share, select Present. Use the left < and right > on-screen controls, or the arrow keys on your keyboard, to scroll through the slides. You also have the option to View presentation in a separate window. To stop sharing the slides, from the toolbar select Stop presenting. <p>Note that the ability to present into a conference may have been restricted to Hosts only.</p>	
<p>View a presentation being shown by another participant</p>	<p>When a participant starts a presentation, you will automatically see the content they are sharing as your main image, and the image of the participants will reduce to a small thumbnail at the top left corner.</p> <p>You can toggle between viewing the presentation and viewing the participants by clicking on the thumbnail.</p> <p>You can also click and drag this window to move it.</p>	p
<p>View a presentation in a separate window</p> 	<p>Whether you are the presenter or a participant, you can view the current presentation in a separate pop-out window.</p> <p>To do this, from the bottom right of the screen select View presentation in new window. To close the window, from the bottom right of the screen select Close separate presentation window.</p>	Shift + P







What	How	Keyboard shortcut
<p>View a presentation at a higher (or lower) refresh rate</p> 	<p>When a participant is showing a presentation, by default you receive it as a series of still images. This is suitable for documents and screens being shared, but if the presentation contains a lot of movement it may appear jerky. If this is the case, you can elect to receive the presentation in full motion as HD video.</p> <p>To do this, from the bottom right of the screen select View full motion presentation. To return to the default view, select View normal presentation.</p>	
<p>Stop/start sending presentation to a participant</p>	<p>(Requires Host privileges)</p> <p>When a participant is sharing a presentation, other participants receive both the presentation and the main video. However, you may want to receive just the main video on a particular endpoint (for example, if you are using a meeting room system for audio and video, but you are already viewing the presentation on your Infinity Connect client, you could stop sending presentation to the meeting room system). To do this, from the Participant list, select the participant and then select Hide presentation here.</p>	
<p>Start sending and receiving video</p> 	<p>(For users who have initially joined without audio and video)</p> <p>From the toolbar at the bottom of the window, select Start Video.</p>	
<p>Start sending and receiving audio</p> 	<p>(For users who have initially joined without audio and video)</p> <p>From the toolbar at the bottom of the window, select Start audio.</p>	
<p>Stop/start sending your video to other participants</p> 	<p>From the toolbar at the bottom of the window, select Turn my camera off or Turn my camera on.</p> <p>Other participants will no longer be able to see you, but you will be able to see them.</p>	
<p>Stop/start sending your audio to other participants</p> 	<p>From the toolbar at the bottom of the window, select Turn my microphone off or Turn my microphone on.</p> <p>Other participants will no longer be able to hear you, but you will be able to hear them.</p>	
<p>Stop/start viewing the video of yourself</p> 	<p>The video of yourself that is being sent to other participants is shown in a thumbnail at the top right of the screen. To hide this, click on the image. It will be replaced by a small Show self view icon; select this to view your image again.</p>	
<p>Show or hide the side panel</p> 	<p>To hide or show the side panel (containing the Participant list tab and the Events tab, and the Control menu), select the Hide side panel < and Show side panel > icons. These will be at the middle left or bottom of the screen, depending on your device and screen width.</p>	




What	How	Keyboard shortcut
View details of events	To see a list of conference events that have occurred during the course of the call (participants joining, leaving, presenting etc.), from the top of the side panel select the Events tab:	Shift + S
View a list of other conference participants	<p>When using Infinity Connect, a list of all other conference participants will be shown in the  Participant list tab of the control panel (which is to the left of or at the bottom of the screen, depending on the screen width). You can scroll through this list to view the names of other participants. You can also search for a particular participant using the Filter by name box at the bottom of the list.</p> <p> The <code>/filter</code> command lets you filter the participant list based on certain criteria such as the participants' role.</p> <p>You can show and hide the side panel by clicking on the Hide side panel < and Show side panel > icons.</p>	
View an individual participant's role	<p>Each person in the Participant list has an icon next to their name, representing their role:</p> <ul style="list-style-type: none">  Hosts, who can control the meeting and other participants  Guests  External Guests, who connected directly to an externally-hosted conference, such as a Microsoft Teams or Skype for Business meeting, or Google Meet. 	
Change a participant's role	<p>(Requires Host privileges; you cannot change your own role to Guest.)</p> <p>From the Participant list, select the participant and then select Make Host or Make Guest.</p> <p>You cannot change the role of External Guest participants (those who are connected directly to an externally-hosted conference, such as a Microsoft Teams or Skype for Business meeting, or Google Meet).</p>	
View individual participant's details	From the Participant list, select the participant and then select Show Info . This brings up an overlay dialog containing details of the participant, including their avatar or image if available (otherwise a placeholder image is shown).	

What	How	Keyboard shortcut
<p>Control another participant's camera</p> 	<p>(Requires Host privileges. This feature must be enabled by an Administrator; not all endpoints can be controlled remotely.)</p> <p>From the participant list, select the participant whose camera you want to control, and then select Camera control (for person-to-person calls, this option is also available via the Camera control button on the toolbar).</p> <p>The Camera Control overlay will appear. Use the buttons to pan, tilt and zoom the camera at the far end. For calls in a Virtual Meeting Room or Virtual Auditorium you can also select Spotlight to bring the participant into the main video window for as long as the Camera Control overlay is open.</p>	
<p>Send and receive chat messages, and share online videos and images</p>	<p>(Available when chat has been enabled by the administrator)</p> <p>All events, including chat messages, are shown in the  Events tab of the side panel (which is to the left of or at the bottom of the screen, depending on the screen width).</p> <p>To send a message, type it in the text box at the bottom of the panel:</p> <div data-bbox="477 768 1029 848" style="border: 1px solid #ccc; border-radius: 10px; padding: 10px; text-align: center; width: fit-content; margin: 10px auto;"> <p>Write a message</p> </div> <p>Messages are visible to everyone else in the conference with a chat-capable client (such as Skype for Business / Lync or Infinity Connect).</p> <p>You can also share videos and images by pasting their URL into the text box.</p>	
<p>Prevent/allow others from joining the meeting</p>	<p>(Requires Host privileges)</p> <p>From the top of the side panel, select Control ● ● ● and then select Lock meeting or Unlock meeting:</p> <p>The impact of locking depends on whether or not the meeting has a Host PIN.</p>	
<p>Allow a participant to join a locked conference</p>	<p>(Requires Host privileges)</p> <p>Participants who are waiting to join a locked conference are shown in the Participant list with a tick and cross next to their names. To allow these participants to join the conference, select the green tick. If you do not want them to join, select the red cross.</p>	

What	How	Keyboard shortcut
Allow waiting Guests to join a new meeting without a Host	<p>(Requires Host privileges)</p> <p>If a Guest joins a meeting without a Host, they will be kept waiting to join until the first Host joins, at which point all waiting Guests will automatically be allowed in to the meeting. However, this only applies if the Host has joined with audio or video; presentation and control-only Hosts will not automatically trigger Guests to join.</p> <p>If you have joined a meeting as a presentation and control-only Host and want Guests to join, from the top of the side panel, select Control ●●● and then select Start the meeting.</p>	<p>Control X</p> <ul style="list-style-type: none">  Lock meeting  Mute all Guests  Disconnect all  Select media devices  Get media stats  Add Participant  Start the meeting
<p>Add a participant to the conference</p> 	<p>(Requires Host privileges)</p> <ol style="list-style-type: none"> From the toolbar at the bottom of the screen, select Add participant. At the prompt, enter the address of the person you want to dial. Select whether you want the participant to have Host or Guest privileges. Select Call in. <p>The call is placed from the conference to the participant and they will appear in the participant list with a green line under their name while their endpoint is ringing. If and when the participant answers the call they will join the conference; if they do not answer, or do not accept the call, they will disappear from the participant list.</p>	
Cancel a call to a participant	<p>(Requires Host privileges)</p> <p>Outbound calls are placed from a Virtual Meeting Room to a participant when a Host uses the Add participant option, or if the Virtual Meeting Room has an automatically dialed participant configured.</p> <p>To cancel an outbound call, from the Participant list, select the participant and then select Cancel Dialout.</p>	
Share a link to the meeting	<p>If you want to send a link to the meeting to someone so that they can join you, select the Share icon at the top left of the screen and then select Copy meeting link.</p> <p>You can then send this link to other participants who can paste it into their browser to join the meeting.</p>	
Mute/unmute another participant	<p>(Requires Host privileges)</p> <p>From the Participant list, select the participant and then select Mute or Unmute.</p> <p>When muted, a  icon is shown next to the participant's name.</p>	

What	How	Keyboard shortcut
<p>Mute all Guest participants</p>	<p>(Requires Host privileges)</p> <p>From the top of the side panel, select Control ● ● ● and then select Mute all Guests.</p>	
<p>Keep a participant in the main video</p>	<p>(Requires Host privileges)</p> <p>From the Participant list, select the participant and then select Spotlight.</p> <p>For more information, see Spotlighting a participant.</p>	
<p>Indicate that you wish to speak</p> 	<p>(Virtual Auditoriums only)</p> <p>From the toolbar at the bottom of the screen, select Raise my hand. The meeting Host will be alerted that your hand is raised. If you no longer wish to speak, you can select the button again to Lower my hand.</p> <p>The meeting Host can also lower your hand.</p>	
<p>View all participants with raised hands</p>	<p>(Virtual Auditoriums only; requires Host privileges)</p> <p>From the top of the side panel, select Control ● ● ● and then select Show hands raised.</p> <p>Participants will be listed in the order that they raised their hand.</p>	
<p>Lower a participant's raised hand</p>	<p>(Virtual Auditoriums only; requires Host privileges)</p> <p>From the Participant list, select the participant and then select Hand down.</p> <p>A participant can also lower their own hand.</p>	

What	How	Keyboard shortcut
<p>Send DTMF tones to another participant (when in a VMR)</p>	<p>(Requires Host privileges; you must be joined over audio, or video and audio)</p> <p>From the Participant list, select the participant and then select Open dialpad. This will open a keypad:</p> 	
<p>Send DTMF tones to the other participant (when in a person-to-person call)</p> 	<p>From the toolbar at the bottom of the window, select Open dialpad. This will open a keypad.</p>	
<p>Transfer a participant to another VMR</p>	<p>(Requires Host privileges)</p> <p>From the Participant list, select the participant and then select Transfer Participant.</p> <p>Enter the alias of the conference you wish to transfer the participant to, the PIN (if applicable) and whether they should join as a Guest or Host, and then select Transfer.</p> <p>You can transfer any participant, including yourself.</p>	
<p>Disconnect another participant</p>	<p>(Requires Host privileges)</p> <p>From the participant list, select the participant's name and then select Disconnect.</p>	
<p>Disconnect all participants (including yourself)</p>	<p>(Requires Host privileges)</p> <p>From the top of the side panel, select Control ● ● ● and then select Disconnect all.</p>	
<p>Disconnect yourself from the conference</p> 	<p>From the toolbar at the bottom of the screen, select Disconnect.</p>	

What	How	Keyboard shortcut																																																						
<p>Mute/unmute the audio coming from the conference</p> 	<p>From the toolbar at the bottom of the screen, select Mute/Unmute incoming audio.</p>																																																							
<p>Change the volume of the audio coming from the conference</p>	<p>From the toolbar at the bottom of the screen, use the slider to adjust the volume level (which is indicated by the green bar under the toolbar).</p> 																																																							
<p>View diagnostic information about your call and client</p>	<p>(Available when connected with audio or video)</p> <p>From the top of the side panel, select Control ● ● ● and then select Get media stats.</p> <p>This brings up an overlay dialog that displays statistics such as the codec being used, incoming and outgoing audio and video bitrates, and how many data packets have been lost and received.</p> <p>It also shows the software version of the client and the Pexip Infinity deployment it is connected to.</p>	 <table border="1"> <caption>Media Statistics</caption> <thead> <tr> <th></th> <th>In</th> <th>Out</th> </tr> </thead> <tbody> <tr> <td>Audio</td> <td></td> <td></td> </tr> <tr> <td>Packets Transmitted</td> <td>9250</td> <td>9291</td> </tr> <tr> <td>Packets Lost</td> <td>0</td> <td>0</td> </tr> <tr> <td>Total Percentage Lost</td> <td>0.0%</td> <td>0.0%</td> </tr> <tr> <td>Recent Percentage Lost</td> <td>0.0%</td> <td>0.0%</td> </tr> <tr> <td>Bitrate</td> <td>158kps</td> <td>158kps</td> </tr> <tr> <td>Codec</td> <td>opus</td> <td>opus</td> </tr> <tr> <td>Video</td> <td></td> <td></td> </tr> <tr> <td>Packets Transmitted</td> <td>8274</td> <td>12950</td> </tr> <tr> <td>Packets Lost</td> <td>25</td> <td>0</td> </tr> <tr> <td>Total Percentage Lost</td> <td>0.0%</td> <td>0.0%</td> </tr> <tr> <td>Recent Percentage Lost</td> <td>0.0%</td> <td>0.0%</td> </tr> <tr> <td>Bitrate</td> <td>1376kps</td> <td>430kps</td> </tr> <tr> <td>Codec</td> <td>H264</td> <td>H264</td> </tr> <tr> <td>Resolution</td> <td>1280x720</td> <td>1280x720</td> </tr> <tr> <td>Configured Bitrate</td> <td>N/A</td> <td>512.0kps</td> </tr> <tr> <td>Decoder Delay</td> <td>5ms</td> <td>N/A</td> </tr> </tbody> </table> <p><small>Software versions: Client version 1.8.1 (chrome #69 on Win32) Server version v20 (45F5B.0.0)</small></p>		In	Out	Audio			Packets Transmitted	9250	9291	Packets Lost	0	0	Total Percentage Lost	0.0%	0.0%	Recent Percentage Lost	0.0%	0.0%	Bitrate	158kps	158kps	Codec	opus	opus	Video			Packets Transmitted	8274	12950	Packets Lost	25	0	Total Percentage Lost	0.0%	0.0%	Recent Percentage Lost	0.0%	0.0%	Bitrate	1376kps	430kps	Codec	H264	H264	Resolution	1280x720	1280x720	Configured Bitrate	N/A	512.0kps	Decoder Delay	5ms	N/A
	In	Out																																																						
Audio																																																								
Packets Transmitted	9250	9291																																																						
Packets Lost	0	0																																																						
Total Percentage Lost	0.0%	0.0%																																																						
Recent Percentage Lost	0.0%	0.0%																																																						
Bitrate	158kps	158kps																																																						
Codec	opus	opus																																																						
Video																																																								
Packets Transmitted	8274	12950																																																						
Packets Lost	25	0																																																						
Total Percentage Lost	0.0%	0.0%																																																						
Recent Percentage Lost	0.0%	0.0%																																																						
Bitrate	1376kps	430kps																																																						
Codec	H264	H264																																																						
Resolution	1280x720	1280x720																																																						
Configured Bitrate	N/A	512.0kps																																																						
Decoder Delay	5ms	N/A																																																						
<p>Use a text-based interface to filter participants and control the conference</p>	<p>Some tasks can be performed using a command-line-style text input from within the Filter by name box at the bottom of the Participant list.</p> <p>Hosts and Guests can filter the list of participants based on criteria such as their role or who is currently speaking. Hosts can also perform other conference control functions such as muting and unmuting participants, spotlighting a participant, and turning the text overlay on and off.</p> <p>To view a full list of available commands, type <code>/</code> into the Filter by name box.</p>																																																							